



myQ X

MyQ OCR Server 3.4

Table of Contents

1	Release Notes	4
1.1	MyQ OCR Server 3.4.....	4
2	System Requirements	5
3	Setting up OCR in MyQ.....	6
3.1	Enable OCR	6
3.2	OCR Folder Structure.....	6
3.3	Manage OCR Profiles	7
4	Installing OCR Server	8
4.1	Install the MyQ OCR Server	8
5	Configuring OCR Server	10
5.1	Tesseract Engine	11
5.2	Supported Languages.....	11
6	Scanning to OCR	16
6.1	Scanning to OCR with Easy Scan.....	16
6.2	About OCR Processing.....	16
6.3	Scan to OCR via Panel Scan (Deprecated)	17
7	Update and Uninstallation.....	18
7.1	Update MyQ OCR Server	18
7.2	Uninstall MyQ OCR Server	18
8	Business Contacts	19

Optical Character Recognition (OCR) is a service that converts scanned documents to a searchable and editable format, such as an MS Word document or a searchable PDF. To employ this functionality in MyQ, you can either use the MyQ OCR server, which is a part of the MyQ solution, or you can use a third-party application.

Unlike third-party OCR applications, the MyQ OCR Server is integrated with the MyQ system, which makes it simple to install and easy to use.

Within the installation of the server, you can utilize the [Tesseract Engine](#) (see page 11).



All changes compared to the previous version are listed in [Release Notes](#) (see page 4).

1 Release Notes

1.1 MyQ OCR Server 3.4

4 August, 2026

Bug Fixes

- PDF files scanned from Kyocera devices are not searchable.
 - Characters in TXT scan output are separated by spaces.
-

2 System Requirements

The following specifications are required to set up and run MyQ OCR Server.

- MyQ X Print Server 10+
- Operating System (64bit):
 - Windows Server 2016, 2019, 2022, and 2025 with all the latest updates.
 - Windows 10, 11, with all the latest updates.
- .NET 8.

 .NET 8 is installed during the installation of the OCR Server. When offline, it must be installed manually prior installation of the OCR Server.

- Required privileges: user with administrator rights.
- Memory for processing multi-page documents: 1 GB RAM minimum, 1.5 GB recommended.
- HDD space: 1.6 GB for the installation.

We recommended to deploy the OCR server on a dedicated server.

OCR Service is registered after the installation and by default it runs under the Local System account.

3 Setting up OCR in MyQ

Configure OCR in MyQ to define where scanned documents are processed and how output formats are handled.

3.1 Enable OCR

1. In the MyQ web UI, go to **MyQ > Settings > Scanning & OCR > OCR**, and ensure that OCR is **Enabled**.

OCR server type: ☒ Custom OCR server
 For example, scans to the profile "Searchable PDF" are stored in a folder according to the profile name "InSearchable PDF". Connect the OCR software to this folder and set the folder to output documents to "Out". Folder locations are relative to the OCR working folder.

☐ MyQ OCR Server

OCR working folder:
 The OCR server needs to be provided with the permission to write to this folder.
 %app% is the MyQ data folder

Profiles: + Add... ✎ Edit 🗑

Name	
The list is empty	

+ Add...

Profiles are available in the Easy Scan terminal action

✓ Save Cancel

2. In **OCR server type**, select *MyQ OCR Server*.
 3. In **OCR working folder**, you can specify the data folder used by the OCR service. We recommended to use the default location (`C:\ProgramData\MyQ\OCR`).
- Note that the **working folder** must also be set in the OCR Server configuration. For more information, see [Configuring OCR Server](#) (see page 10).



Both the MyQ server and the OCR server must have read and write access to the OCR working folder.

3.2 OCR Folder Structure

The OCR folder (default is `C:\ProgramData\MyQ\OCR`) contains the following sub-folders:

- **/in** – stores scanned documents before processing.
- **/out** – stores scanned documents after processing. These files are ready to be sent.
- **/profiles** – stores your OCR profiles.

3.3 Manage OCR Profiles

Profiles define the output format of scanned document, and are used by **Easy Scan** and email commands.

3.3.1 Create a profile

1. Click **+Add** next to **Profiles**.

A new item with the settings of the new profile appears in the list below.

2. Type the **Name** of the profile, select the **Output format** from the list, and click **OK**. The profile is saved.

3.3.2 Edit a profile

1. Select the profile on the list and click **Edit** (or right-click and select **Edit** in the shortcut menu).
2. In the profile editing options, you can change the name and the output format of the profile.

3.3.3 Delete a profile


To delete a profile, select it and click the delete icon on the ribbon (or right-click and select **Delete** in the context menu).

Click **Save** at the bottom of the screen to save your changes.

4 Installing OCR Server

4.1 Install the MyQ OCR Server

1. Download the latest available version of the MyQ OCR Server from the MyQ Community portal.
2. Run the executable file. The OCR Server installation window appears.



3. Select the folder where you want to install the OCR server. The default path is:
`C:\Program Files\MyQ OCR Server\`
4. Accept the license terms and conditions to continue with the installation. Then click **INSTALL**. The OCR server is installed.
5. Click **Finish** to leave the installation wizard. The configuration window of the OCR server appears. The configuration steps are described below.

i In case the file is blocked from your browser or OS, click **Run** or **Allow**, or modify your Windows Security settings to allow the installation of unknown apps (turn off **App & browser control**).
If you get the “*Windows protected your PC*” message when trying to run the file, click **More info**, and then click **Run anyway**, to begin the installation.

If you still cannot run the file, right click on it, and select **Properties**. In the **General** tab, next to **Security**, mark the **Unblock** checkbox, click **Apply**, and then **OK**. Run the file again and begin the installation.

5 Configuring OCR Server

To configure MyQ OCR Server, use the OCR Server configuration window that opens automatically after the MyQ OCR Server installation completes. To open it directly, go to Windows apps and select **MyQ OCR Server Settings**.

In the configuration window, you can also stop and start the Windows service of the OCR server, and open logs.

OCR Server

Service status: **Running** [Logs](#) **Stop**

Languages: Čeština

- ☐ Basa Sunda
- ☐ Bosanski (босански)
- ☐ Brezhoneg
- ☐ Català
- ☒ Čeština
- ☐ Cymraeg
- ☐ Српски
- ☐ Dansk
- ☐ Deutsch
- ☐ Èdè Yorùbá

It is not recommended to select more than 3 languages for best performance and accuracy

Working folder: **...**

Username:

Password:

Apply

- **Languages** - While you can select all the [Supported Languages](#) (see page 11), we recommend to select only those that are likely to be used within the OCR process. Selecting fewer languages increases the speed and accuracy of the OCR process.
- **Working folder** - This is the folder where the OCR server and the MyQ server exchange the OCR scanned files. This value must be the same as OCR working

folder that you set in **MyQ > Settings > Scanning & OCR**. In case you use a shared folder, enter the **Username** and **Password** for access to the folder.



Both the MyQ server and the OCR server must have read and write access to the OCR working folder.

Click **Apply** for your changes to take effect.

To open the log files, click **Logs** at the top-right corner of the OCR Server configuration window.

To stop or restart the OCR Server Windows service, click **Stop** (or **Start**) at the top-right corner of the OCR Server configuration window. You can also manage the service in the Windows Task Manager, where it is called `OCRSERVICE`.

5.1 Tesseract Engine

Tesseract is an open source Optical Character Recognition (OCR) engine, which is used by MyQ in the MyQ OCR Server.

The Tesseract OCR engine supports the following formats:

- *PDF*
- *PDF/A* (the compliance level of PDF/A is **PDF/A-1B**)
- *TXT*

Tesseract can be used to process documents in many language – for more information, see [Supported Languages](#) (see page 11).



For further information about the Tesseract engine, see the dedicated documentation from its developer.

5.2 Supported Languages

The following languages are supported and can be processed by the Tesseract OCR engine used by the MyQ OCR Server:

Language	Language Code
Afrikaans	afr
Albanian	sqi

Language	Language Code
Arabic	ara
Azerbaijani	aze
Belarusian	bel
Bosnian	bos
Breton	bre
Bulgarian	bul
Catalan	cat
Cebuano	ceb
Corsican	cos
Croatian	hrv
Czech	ces
Danish	dan
Dutch, Flemish	nld
English	eng
Middle English (1100-1500)	enm
Esperanto	epo
Estonian	est
Faroese	fao
Filipino	fil
Finnish	fin
French	fra
Scottish Gaelic	gla

Language	Language Code
Galician	glg
German	deu
Haitian	hat
Hebrew	heb
Hungarian	hun
Icelandic	ici
Indonesian	ind
Irish	gle
Italian	ita
Japanese	jpn
Javanese	jav
Kyrgyz	kir
Latin	lat
Latvian	lav
Lithuanian	lit
Luxembourgish	ltz
Macedonian	mkd
Malay	msa
Maltese	mlt
Māori	mri
Norwegian	nor
Occitan	oci

Language	Language Code
Polish	pol
Portuguese	por
Quechua	que
Romanian, Moldovan	ron
Russian	rus
Serbian	srp
Serbian Latin	srp_latn
Slovak	slk
Slovenian	slv
Spanish	spa
Sundanese	sun
Swahili	swa
Tajik	tgk
Tonga	ton
Turkish	tur
Ukrainian	ukr
Uzbek	uzb
Uzbek Cyrillic	uzb_cyrl
Vietnamese	vie
Welsh	cym
Western Frisian	fry
Yoruba	yor

Language	Language Code
Georgian	geo

 Selecting multiple languages will take much more time to process the files.

6 Scanning to OCR

To scan documents using OCR, create and configure Easy Scan actions that send scans to specific OCR profiles (or let users choose the output format).

6.1 Scanning to OCR with Easy Scan

The MyQ administrator can create any number of **Easy Scan** terminal actions for scanning to OCR. They can either create one **Easy Scan** action for each output or let the scanning user select the format themselves.

To enable users to scan to a specific profile, select the profile (such as *ocrpdf* or *ocrtxt*) as the **Format** parameter of the **Easy Scan** action.

The screenshot shows a 'Format' configuration window. It has a title field set to 'Format', a 'Type' dropdown set to 'Code List', and a 'Code Book' dropdown set to 'Format'. The 'Default value' dropdown is open, showing a list of options: PDF, JPEG, TIFF, XPS, HCPDF, Default, OCRPDF, OCRPDFA, and OCRTXT. The 'OCRPDF' option is highlighted in blue. There are also checkboxes for 'Required' and 'Prohibit change of value', both of which are checked. An 'Advanced' section is expanded, showing a 'Reference' field with a red arrow pointing to the 'OCRPDF' option in the list.

You can also enable users to select the profile themselves. For more information about how to set up the **Easy Scan** action on a MyQ Embedded terminal, see (10.2) OCR in the Print Server guide.

6.2 About OCR Processing

The OCR software listens to the document sub-folders of the **\in** folder (*in\pdf*, *in\text*,...), processes the file that was sent there, saves the converted document to the **\out** folder and then deletes the source file from the **\in** folder.

MyQ listens to the **\out** folder, sends the converted file to the user and deletes it from the folder. The converted file is sent to the folder listed in the **User's storage** text box, in the user properties panel.

The file sent to the **\out** folder by the OCR software must have the same name as the source file in the **\in***** folder. If the name of the converted file differs from the source file, it is deleted without being sent to the user.

6.3 Scan to OCR via Panel Scan (Deprecated)

 Support for scanning to OCR via Panel Scan was removed in MyQ Print Server 10.2. Use Easy Scan instead.

To send the scanned document for processing by the OCR server, the user must type the receiver email address in the form: `myqocr.*profilename*@myq.local`, where `*profilename*` is the name of the profile (case sensitive) for the requested output.

The document is converted by the MyQ OCR Server and sent to the folder or email address that is set in the **User's storage** text box on the user's properties panel in the MyQ web administrator interface.

7 Update and Uninstallation

This section describes how to update and uninstall MyQ OCR Server.

7.1 Update MyQ OCR Server

Download and run the latest available version of the MyQ OCR Server from the MyQ Community portal. The update process in the update wizard is identical to the MyQ OCR Server installation.

7.2 Uninstall MyQ OCR Server

You can uninstall the MyQ OCR Server via the Windows Control Panel.

Go to **Control Panel > Programs and Features**, find and select the MyQ OCR Server application on the list, and click **Uninstall** on the ribbon (or right-click and select **Uninstall**).

8 Business Contacts

MyQ® Manufacturer	MyQ® spol. s r.o. Harfa Business Center, Ceskomoravska 2532/19b, 190 00 Prague 9, Czech Republic ID no. 615 06 133 MyQ® spol. s r.o. is registered in the Commercial Register at the Municipal Court in Prague, file no. C 29842 (hereinafter as "MyQ®")
Business information	http://www.myq-solution.com info@myq-solution.com¹
Technical support	support@myq-solution.com²
Notice	MANUFACTURER WILL NOT BE LIABLE FOR ANY LOSS OR DAMAGE CAUSED BY INSTALLATION OR OPERATION OF THE SOFTWARE AND HARDWARE PARTS OF THE MyQ® PRINTING SOLUTION. This manual, its content, design and structure are protected by copyright. Copying or other reproduction of all or part of this guide, or any copyrightable subject matter without the prior written consent of MyQ® is prohibited and can be punishable. MyQ® is not responsible for the content of this manual, particularly regarding its integrity, currency and commercial occupancy. All the material published here is exclusively of informative character. This manual is subject to change without notification. MyQ® is not obliged to make these changes periodically nor announce them, and is not responsible for currently published information to be compatible with the latest version of the MyQ® printing solution.

1. <mailto:info@myq-solution.com>

2. <mailto:support@myq-solution.com>

Trademarks	“MyQ®”, including its logos, is a registered trademark of MyQ®. Any use of trademarks of MyQ® including its logos without the prior written consent of MyQ® Company is prohibited. The trademark and product name are protected by MyQ® and/or its local affiliates.
-------------------	---



SAVE TIME WITH **PERSONALIZED** PRINT SOLUTIONS

MyQ X is an award-winning on-premise or private cloud print management solution trusted by millions of users.



info@myq-solution.com



myq-solution.com


50+ million
Trusted users

1+ million
Active devices

26+
Brands supported

1000+
Certified partners

Operating in **140+**
countries



Awarded and certified

